



Home



Archives



Downloads



Links



AboutUs

funky

1/6/2002

Free  
e-News  
click here  
to subscribe



## AccuDraw Reset

[V8 Version - V08.00.00.00 - 01.06.02](#)

[J Version - V01.00.00.00 - 11.29.00](#)

[SE Version - V01.00.00.00 - 11.30.00](#)

adrst.ma (adrstSE.ma, adrstv8.ma) is the mdl application. Put this file into the MicroStation mdlapps/ directory. If you prefer to have the AccuDraw Reset application load when MicroStation starts, then put the adrst.ma file into the mdlsys/required/ directory.

Load command: [MDL LOAD ADRST](#)

Unload command: [MDL UNLOAD ADRST](#)

Commands:  
NONE

### Workflow:

The application runs as soon as it is loaded. No dialogs or commands will be available. The application monitors the input events performed by the user. If the reset button on the mouse is clicked the application moves the focus to the AccuDraw dialog by calling the accudraw command.

Some MicroStation applications may also use the monitoring features. Conflicts may arise in these instances. Please be sure to test the interaction between adrst.ma and your current environment thoroughly prior to deploying the application.

[\[Return to Free Download Reference Index\]](#)





[Home](#) | [Archives](#) | [Free Downloads](#) | [Links](#) | [Mail](#) | [Advertise](#)

Copyright © 1998-2001 Ramsey Systems, Inc. All rights reserved. [privacy](#) | [legal](#).