

[Home](#)[Archives](#)[Downloads](#)[Links](#)[AboutUs](#)

9/12/2001

Free  
e-News  
click here  
to subscribe

### AccuDraw Reset

[download J Version - V01.00.00.00 - 11.29.00](#)

[SE Version - V01.00.00.00 - 11.30.00](#)



adrst.ma is the mdl application. Put this file into the MicroStation mdlapps/ directory. If you prefer to have the AccuDraw Reset application load when MicroStation starts, then put the adrst.ma file into the mdlsys/required/ directory.

The commands in this document are not linked to other pages. These are MicroStation keyins. If you are using MicroStation link to view this page then you can click on the linked text to start the command. But before this will work you need to visit the [download.htm](#) page and get the self extracting zip file for this application. The cad gurus suggest that you create a download directory for the application and extract the files into this new directory. When the files have been extracted you can copy or move the \*.ma file to the mdlapps directory.

Load command: [MDL LOAD ADRST](#)

Unload command: [MDL UNLOAD ADRST](#)

Commands:  
NONE

#### Workflow:

The application runs as soon as it is loaded. No dialogs or commands will be available. The application monitors the input events performed by the user. If the reset button on the mouse is clicked the application moves the focus to the AccuDraw dialog by calling the accudraw command.

Some MicroStation applications may also use the monitoring features. Conflicts may arise in these instances. Please be sure to test the interaction between adrst.ma and your current environment thoroughly prior to deploying the application.

[\[Return to Free Download Reference Index\]](#)



[Home](#) | [Archives](#) | [Free Downloads](#) | [Links](#) | [Mail](#) | [Advertise](#)

Copyright © 1998-2001 Ramsey Systems, Inc. All rights reserved. [privacy](#) | [legal](#).